

XRDP

- Step 1: Install Xfce4 and xRDPFirst, open your terminal and install the desktop environment and xRDP packages (these examples use Debian/Ubuntu-based distributions):

```
sudo apt update
sudo apt install xfce4 xfce4-goodies xrdp -y
```

- Step 2: Configure the Desktop Session. You need to tell the xRDP server to load the Xfce desktop environment instead of the default Linux desktop. Set Xfce4 as the default for your active user by running:

```
echo "xfce4-session" > ~/.xsession
```

- Make the file executable:

```
chmod +x ~/.xsession
```

- Step 3: Edit the xRDP Startup ScriptTo prevent session dropouts, update the global xRDP configuration file:Open the file with your preferred text editor (e.g., nano):

```
sudo nano /etc/xrdp/startwm.sh
```

- Comment out the last two lines by adding a # at the beginning, so they look like this:

```
# test -x /etc/X11/Xsession && exec /etc/X11/Xsession
# exec /bin/sh /etc/X11/Xsession
```

- Add startxfce4 right before the last line of the file (usually exit 0), ensuring your file ends similarly to this:

```
startxfce4
exit 0
```

- Save and close the file.
- Step 4: Add the xRDP User to the SSL Cert Group
On some systems (like newer Ubuntu versions), the xrdp user needs permission to read the SSL certificates, otherwise, you might experience black screen issues:

```
sudo adduser xrdp ssl-cert
```

- Step 5: Restart the Service and Open the Firewall. Restart the xRDP service to apply all configuration changes:

```
sudo systemctl restart xrdp
```

- If you are using a firewall (such as ufw), make sure to open the RDP port so your remote device can connect:

```
sudo ufw allow 3389
```

Use code with caution. Step 6: Connect You can now open the Remote Desktop Connection app on Windows or the Microsoft Remote Desktop app on macOS/Linux. Enter your Linux computer's IP address and log in using your standard Linux username and password. If you're having trouble connecting or seeing a black screen, let me know: What Linux distribution and version are you using (e.g., Ubuntu 24.04, Debian 12)? Are you connecting from a Windows, Mac, or Linux client? 15 sites How to switch from gnome to xfce for xrdp? To switch from Gnome to xfce for xrdp on Debian, you can try these steps: 1. Modify `/etc/xrdp/startwm.sh` 2. Comment out the last... Reddit Cannot connect to Xfce with remote desktop If you're having trouble connecting to Xfce with remote desktop on Xubuntu, you can try these steps: * **Edit /etc/xrdp/startwm.sh... Ask Ubuntu** **Install and configure xrdp to use Remote Desktop with Ubuntu** **Install a desktop environment on your Linux VM** * `ssh azureuser@myvm.chinanorth2.cloudapp.chinacloudapi.cn`. If you're using Windows... Azure.cn * **xrdp certificate mismatch ===== Self-signed certificates ===== Trust the Existing Self-Signed Certificate =====** * **Launch your Remote Desktop Connection** and enter the server's hostname. * **Click View Certificate** on the security warning prompt. * **Go to the Details tab and click Copy to File.** * **Save the .cer file to your local computer.** * **Double-click the saved .cer file, click Install Certificate, choose Local Machine, and select Place all certificates in the following store. Browse and pick the Trusted Root Certification Authorities** store, then finish the import.**

Hostname changed

If the hostname has changed you need to re-issue the self-signed certificate:

```
sudo make-ssl-cert generate-default-snakeoil --force-overwrite
```

From:

<https://wiki.condrau.com/> - **Bernard's Wiki**

Permanent link:

<https://wiki.condrau.com/deb13:xrdp?rev=1783705539>

Last update: **2026/07/11 00:45**

