

TightVNC Server

Installation

Install:

```
# apt-get install tightvncserver
# echo 'update-alternatives: using /usr/bin/tightvncserver to provide
/usr/bin/vncserver (vncserver) in auto mode'
# echo 'update-alternatives: using /usr/bin/Xtightvnc to provide
/usr/bin/Xvnc (Xvnc) in auto mode'
# echo 'update-alternatives: using /usr/bin/tightvncpasswd to provide
/usr/bin/vncpasswd (vncpasswd) in auto mode'
```

Configure: Modify file `~/.vnc/xstartup` as follows and restart the vnc server

```
$ vim ~/.vnc/xstartup

#!/bin/sh
xrdb $HOME/.Xresources
xsetroot -solid grey
#x-terminal-emulator -geometry 80x24+10+10 -ls -title "$VNCDESKTOP Desktop"
&
#x-window-manager &
# Fix to make GNOME work
#export XKL_XMODMAP_DISABLE=1
/etc/X11/Xsession
```

Test:

```
$ tightvncserver -kill :1
$ tightvncserver -geometry 1024x768
```

Add a script to `/etc/init.d/`:

```
#!/bin/bash

case "$1" in
start)
/usr/bin/tightvncserver -geometry 1024x768 :1
/usr/bin/tightvncserver -geometry 1600x900 :2
;;

stop)
/usr/bin/vncserver -kill :1
/usr/bin/vncserver -kill :2
;;
```

```
restart)
$0 stop
$0 start
;;

esac
exit 0
```

Start 2 VNC instances to have the best resolution available on different devices, e.g. iPad and Computer

Links

- [How To Set Up VNC Server on Debian](#)
- [CentOS - VNC \(Virtual Network Computing\)](#)

From:
<https://wiki.condrau.com/> - **Bernard's Wiki**



Permanent link:
<https://wiki.condrau.com/deb720:vnc>

Last update: **2017/05/07 14:23**